



# ADDENDUM TO THE DL-WINDOWS v3.5.3 SOFTWARE INSTALLATION INSTRUCTIONS

Due to recent changes in the Microsoft Installation Installer, update previous versions of DL-Windows to version 3.5.3 as follows:

## A. INSTALL DL-WINDOWS v3.5.3

1. Insert the DL-Windows 3.5.3 installation disk into your CD-ROM drive. Follow the Installation Wizard instructions; when installation is complete, do NOT remove the installation disk from the drive.
2. Double-click the DL-Windows desktop icon *while the DL-Windows disk is in the drive*. The installation software will take the extra steps necessary to fully update the previous version of DL-Windows to version 3.5.3.
3. At the end of the installation, DL-Windows will run.
4. If *XP Styles* are enabled, a "Please Turn Off XP Styles" popup message will appear. Click **Yes** for instructions to turn off XP Styles.
5. A DL-Windows Log In screen opens. Press **Enter**.  
**Note:** Pre-existing Accounts will not be loaded; therefore exit DL-Windows and run the Import Utility as described below.

## B. RUN THE IMPORT UTILITY

1. Click **Start, Programs, DL-Windows, Import Utility**.
2. Click **OK** to the *Welcome to DL-Windows Import Utility...* popup.
3. Click **Open**. The **Locate your AL3000/AcctList File** dialog opens.
4. Click the **Files of Type** drop down list, select **Old DL-Windows Index**.
5. Click the file **AL3000.MDB**.
6. Click **Open**.
7. Click **Update**.
8. Click **Yes** to confirm the update.
9. Click **OK** to the **Import Utility** message.
10. Click **OK** to the **Update Successful** message. You can now close the *Import Utility* and run the DL-Windows software program.

333 Bayview Avenue  
Amityville, New York 11701  
For Sales and Repairs, (800) 645-9445  
For Technical Service, (800) 645-9440  
Publicly traded on NASDAQ      Symbol: NSSC